

SUPER COPIER SYSTEM EA DASHBOARD AND INPUT DOCS

Super Copier System EA
Contact Info
beyondream2011@gmail.com

SETTINGS & INFO

	BP	SP	TP	BL	SL	TL	Profit
Signal #1 ON/OFF Copy Scale: 1.0	4	13	17	0.04	0.13	0.17	11.32
Signal #2 ON/OFF Copy Scale: 1.0	5	0	5	0.14	0.00	0.14	-10.74
Signal #3 ON/OFF Copy Scale: 1.0	0	0	0	0.00	0.00	0.00	0.00
Signal #4 ON/OFF Copy Scale: 1.0	0	0	0	0.00	0.00	0.00	0.00
Signal #5 ON/OFF Copy Scale: 1.0	0	10	10	0.00	0.14	0.14	9.43

STATUS

Stop DD: 30.00% (\$923.34)
Total Profit: 10.52

EA

Contact Info

Signal #1/2/3/4/5

ON/OFF: turn on/off

(switch in input parameter)

ON: copy this signal

OFF: not copy this signal

Copy Scale:

Default: 1

This input is used to calculate the copy trade lot size.

Formula:

Copy Trade Lot = Copy Scale * Signal Trade Lot * User Balance / Signal Balance

e.g. Signal balance = \$1000, signal trade lot = 0.1

Copy Scale = 1, user balance = \$1000, copy trade lot is 0.1

Copy Scale = 1.5, user

balance = \$1000, copy trade lot is

0.15

Stop DD: max DD (loss) to stop EA
30% is referring to 30% of balance.

Total Profit:
Total profit from all copy trade from all signals

- . BP: Buy Positions
- . SP: Sell Positions
- . TP: Total Positions
- . BL: Buy Lots
- . SL: Sell Lots
- . TL: Total Lots
- . Profit

Example:
 4 buy positions from Signal#1
 13 sell positions from Signal#1
 17 total positions from Signal#1
 0.04 buy lots from Signal#1
 0.13 sell lots from Signal#1
 0.17 total lots from Signal#1
 \$11.32 total profit from Signal#1

Input Parameters:

- **Symbol Prefix**
- **Symbol Suffix**

Some of the brokers offer non-standard symbol, which is with prefix and/or suffix. Such as "iEURUSD" , "EURUSD_pro" . If that is the case, the prefix and/or suffix string is required to add in the symbol prefix and symbol suffix input.

Example:

- "iEURUSD" : add i in Symbol Prefix
- "EURUSD_pro" : add _pro in Symbol Suffix

Simply leave them as blank if the symbol is standard without prefix or suffix. Noted that the prefix/suffix might be a dot such as "EURUSD." , be reminded to notice that and add it.

- **Stop DD: max DD (loss) to stop EA:**

30=30% of balance. Once accumulated loss (including closed order in loss) exceeds this limit, all order open by this EA will be closed and EA will stop running.

- **Copy Signal#1/2/3/4/5**

True : Copy

False : Not Copy

- **Copy Existing Trades of Signal #1/2/3/4/5**

Existing trades: opening trade(s) on signal before loading EA

True : Copy

False : Not copy

- **Copy Scale of Signal #1/2/3/4/5**

Kindly refer the formula and example of copy scale calculation

Expert - Super Copier EA en v10

About Common Inputs

Variable	Value
 Symbol Prefix	
 Symbol Suffix	
 Stop DD,30=30%, Loss exceeds this limi...	30.0
 Copy Signal #1	false
 Copy Signal #2	false
 Copy Signal #3	false
 Copy Signal #4	false
 Copy Signal #5	false
 Copy Existing Trades of Signal #1	true
 Copy Existing Trades of Signal #2	true
 Copy Existing Trades of Signal #3	true
 Copy Existing Trades of Signal #4	true
 Copy Existing Trades of Signal #5	true
 Cope Scale of Signal #1	1.0
 Cope Scale of Signal #2	1.0
 Cope Scale of Signal #3	1.0
 Cope Scale of Signal #4	1.0
 Cope Scale of Signal #5	1.0